


Step 0: download the newest Xerox print drivers for Mac OS from <http://www.support.xerox.com/> (usually called: "Mac OS Common Print Driver Installer"). Search for e.g. the model name of the printer, i.e. 'AltaLink C8045' with a built-in controller, and download the driver installer package. Install the driver(s) - this covers most Xerox printers!

Step 1: open 'System Preferences' -> 'Printers & Scanners' and press the '+' sign at the bottom to add a printer. Choose the tab 'IP' and fill in the fields according this picture:




Address: cups1.compute.dtu.dk
Protocol: IPP
Queue: printers/name_of_the_queue , where name_of_the_queue is e.g. cm303151a as above


NOTE: the queue name is 'printers/' and the name of the queue!!!

Name: name of the printer on your system
Location: building and room (optional)
Use: click on 'Select Software ...' and find the model name of the printer, in this case the 'Xerox AltaLink C8045'


Click on 'Add'. If you already have another printer that uses the CUPS server, you will probably see a warning like this:



Click on 'Continue' - and the printer will be added, i.e. you will see something like this:



Click on 'Options & Supplies' and then on 'Options' in the new window. Choose the right options for the printer, e.g. for the AltaLink C8045 the 'Office Finisher LX with ...':



You can always return to this screen via the 'System Preferences', if you want/need to make changes.

Press 'OK' - and you are done!

Using the Xerox printer: when printing from an application, choose the printer, and adjust the options under 'Xerox Features', e.g. 2-sided print and stapling. This is shown here:

Printer: Xerox 303-153

Presets: Default Settings

Copies: 1 Two-Sided

Pages: All
 Selected Pages in Sidebar
 From: 1 to: 1

Paper Size: A4 210 by 297 mm

Orientation:  

Xerox Features

Paper/Output

Job Type:  Normal Print

Paper:  - White
- Printer Default Type

2-Sided Printing:  2-Sided Print

Finishing:  - 1 Staple
- No Folding


Xerox Black and White:  Off (Use Document C...

Print Quality:  Standard

Output Destination:  Automatic



To save paper, disable the 'Banner page'! Click on the 'half green' square at the bottom, and change the banner page option:



Click 'OK' - and then 'Print'! Done!

Note: the driver will remember your settings, until you change them!